



在 Windows Live Mail 2011 上設定電子郵件帳號的步驟：

1. 點選 <帳戶>
2. 點選 <電子郵件>



3. 電子郵件地址：輸入電子郵件地址 (例：user@example.com)
4. 密碼：輸入電子郵件帳號密碼
5. 按 <記住此密碼>
6. 你傳送郵件的顯示名稱：輸入顯示名稱 (例：Display Name)
7. 點選 <手動設定伺服器設定>
8. 按 <下一步>




The screenshot shows the 'Add New Email Account' window in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is '新增電子郵件帳戶' (Add New Email Account). Below the heading, there is a note: '如果您擁有 Windows Live ID，請立即登入。否則可在稍後建立一個 ID。' (If you have a Windows Live ID, please log in immediately. Otherwise, you can create one later.) and a link '登入 Windows Live' (Log in to Windows Live). The form contains several fields and options:


- '電子郵件地址:' (Email address): A text box containing 'user@example.com' with a red box and the number '3' around it.
- '密碼:' (Password): A text box with masked characters '.....' with a red box and the number '4' around it.
- '記住此密碼(B)' (Remember this password): A checked checkbox with a red box and the number '5' around it.
- '您傳送郵件的顯示名稱:' (Display name): A text box containing 'Display Name' with a red box and the number '6' around it.
- '手動設定伺服器設定(C)' (Manually configure server settings): A checked checkbox with a red box and the number '7' around it.
- At the bottom right, there are two buttons: '取消' (Cancel) and '下一步' (Next). The 'Next' button is highlighted with a red box and the number '8' around it.

On the right side of the form, there is a text block: '大多數電子郵件帳戶皆可使用 Windows Live Mail 郵件軟體，包括 Hotmail Gmail 以及其他服務。' (Most email accounts can use Windows Live Mail email software, including Hotmail Gmail and other services.)

9. 伺服器類型：點選 <IMAP>
10. 伺服器位址：輸入 <域名 (除去”點”)> .securemail.hk (例：examplecom.securemail.hk)
11. 連接埠：輸入 <993>
12. 點選 <需要安全連線(SSL)>
13. 點選 <純文字>
14. 登入使用者名稱：再次輸入電子郵件地址 (例：user@example.com)
15. 伺服器位址：輸入 smtp.u328.com
16. 連接埠：輸入 <1025>
17. 取消點選 <需要安全連線(SSL)>
18. 點選 <需要驗證>
19. 點選 <下一步>



20. 按 <完成>




21. 點選 <帳戶>

22. 點選 <內容>




23. 按 <伺服器>

24. 按 <設定>



25. 點選 <登入方式>
26. 帳戶名稱：輸入 SMTP 帳號名稱(例：smtp@example.com)
27. 密碼：輸入 SMTP 帳號密碼
28. 點選 <記住密碼>
29. 按 <確定>



30. 完成

- 完 -