

在 IOS11 (iPhone / iPad)上設定電子郵件帳號的步驟：

1. 在主畫面上選擇 <設定>
2. 按<帳戶及密碼>
3. 按<加入帳戶>






UDomain Web Hosting Company Ltd.  
Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon  
Tel : (852) 2554 7545  
Fax : (852) 2554 7215  
Email : service@udomain.hk  
Web : www.udomain.hk

4. 按<其他>

5. 按<新增郵件帳號>



6. 名稱：輸入顯示名稱 (例：Display Name)
7. 電子郵件：輸入電子郵件地址 (例：user@example.com)
8. 密碼：輸入電子郵件帳號密碼
9. 描述：輸入電子郵件地址 (例：user@example.com)
10. 按<下一步>



The screenshot shows a form titled '新增帳號' (Add Account) with a '取消' (Cancel) button on the left and a '10 下一步' (Next) button on the right. The form contains four input fields, each with a red box and a number indicating the step:

Field Label	Input Value	Step Number
名稱	Display Name	6
電子郵件	user@example.com	7
密碼	●●●●●●●●	8
描述	user@example.com	9



UDomain Web Hosting Company Ltd.  
Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon  
Tel : (852) 2554 7545  
Fax : (852) 2554 7215  
Email : service@udomain.hk  
Web : www.udomain.hk

**11. 點選 <IMAP>**

**12. 收件伺服器主機名稱: 輸入 <域名 ( 除去"點" ) >.securemail.hk**

(例 : examplecom.securemail.hk)

**13. 使用者名稱: 輸入電子郵件地址 (例 : user@example.com)**

**14. 密碼 : 輸入電子郵件帳號密碼**

**15. 寄件伺服器主機名稱\*: 輸入 ud.1025.hk**

\*假如尚未登記 SMTP 服務 · 請聯絡  
UDomain 客戶服務部了解登記詳情:  
電話:2554 7545 電郵地  
址:service@udomain.com.hk

**16. 使用者名稱: 輸入電子郵件地址 (例 : user@example.com)**

**17. 密碼 : 輸入電子郵件帳號密碼**



18.按<儲存>

19.按剛才建立的電子郵件帳號(例：user@example.com)



20.再按剛才建立的電子郵件帳號(例：user@example.com)






UDomain Web Hosting Company Ltd.  
Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon  
Tel : (852) 2554 7545  
Fax : (852) 2554 7215  
Email : service@udomain.hk  
Web : www.udomain.hk

21. 按 SMTP <ud.1025.hk >

22. 再按 < ud.1025.hk >





UDomain Web Hosting Company Ltd.  
Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon  
Tel : (852) 2554 7545  
Fax : (852) 2554 7215  
Email : service@udomain.hk  
Web : www.udomain.hk

23.開啟<使用 SSL>

24.伺服器傳輸埠：輸入 1025

25.點選 <完成>

26.按<進階>

The screenshot shows two panels of the UDomain account setup interface. The left panel is titled 'ud.1025.hk' and contains the following fields: '伺服器' (Server) with a toggle switch, '寄件伺服器' (Outgoing Server) section with '主機名稱' (Host Name) set to 'ud.1025.hk', '使用者名稱' (Username) set to 'user@example.com', '密碼' (Password) field, '使用 SSL' (Use SSL) with a toggle switch (callout 23), '認證' (Authentication) dropdown set to '密碼', and '伺服器傳輸埠' (Server Port) set to '1025' (callout 24). A '25 完成' (25 Done) button is at the top right of this panel. The right panel is titled '帳號' (Account) and contains: 'IMAP 帳號資訊' (IMAP Account Info) section with '名稱' (Name) 'Display Name', '電子郵件' (Email) 'user@example.com', and '描述' (Description) 'user@example.com'; '收件伺服器' (Incoming Server) section with '主機名稱' (Host Name) 'examplecom.securemail.hk', '使用者名稱' (Username) 'user@example.com', and '密碼' (Password) field; and '寄件伺服器' (Outgoing Server) section with 'SMTP' set to 'ud.1025.hk'. A '26 進階' (26 Advanced) button is at the bottom left of this panel. A '完成' (Done) button is at the top right of the right panel.



UDomain Web Hosting Company Ltd.  
Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon  
Tel : (852) 2554 7545  
Fax : (852) 2554 7215  
Email : service@udomain.hk  
Web : www.udomain.hk

27.開啟<使用 SSL>

28.伺服器傳輸埠：輸入<993>

29.點選 <帳號>

The screenshot shows the 'Account' (帳號) settings page in a mobile app. The page title is '進階' (Advanced). It features several sections: '將不要的郵件移到:' (Move unwanted mail to:) with options for '已刪除的信箱' (Deleted mailbox) and '封存信箱' (Archive mailbox); '已刪除的郵件' (Deleted mail) with a '移除' (Remove) button and a '一週後 >' (After one week >) option; '收件設定' (Incoming mail settings) with a toggle for '使用 SSL' (Use SSL) which is turned on and marked with a red box and number 27; '認證' (Authentication) with a '密碼 >' (Password >) option; 'IMAP 路徑前置碼 /' (IMAP path prefix /); '伺服器傳輸埠 993' (Server port 993) which is marked with a red box and number 28; and 'S/MIME' with a toggle switch.





UDomain Web Hosting Company Ltd.

Unit A-D, 6/F, Wing Cheung Industrial Building,  
No. 109 How Ming Street,  
Kwun Tong, Kowloon

Tel : (852) 2554 7545

Fax : (852) 2554 7215

Email : service@udomain.hk

Web : www.udomain.hk

### 30.按<完成>

A screenshot of an email account configuration interface. At the top, there are buttons for '取消' (Cancel) on the left and '完成' (Done) on the right, with a small red '30' icon next to '完成'. The main content is organized into sections: 'IMAP 帳號資訊' (IMAP Account Information) with fields for '名稱' (Name) set to 'Display Name', '電子郵件' (Email) set to 'user@example.com', and '描述' (Description) set to 'user@example.com'; '收件伺服器' (Incoming Server) with fields for '主機名稱' (Host Name) set to 'examplecom.securemail.com', '使用者名稱' (Username) set to 'user@example.com', and '密碼' (Password) shown as dots; '寄件伺服器' (Outgoing Server) with a field for 'SMTP' set to 'ud.1025.hk'; and a final '進階' (Advanced) button at the bottom.

- 完 -